

Roles & Permissions

Roles allow administrators to apply a specified set of permissions to individual users and groups, allowing administrators to specify exactly what each user can see and do. Each user or group can have multiple roles.

- [Permission Grouping](#)
- [Permission Definitions](#)
- [Creating & Editing a Role](#)
- [Deleting Roles](#)

The Roles page can be found in the administration menu under **Security**. The roles page lists all the roles in Continua and allows you to create, edit and delete them.

Administration																																																						
Projects	Roles [Create] <table><tr><th>Name</th><th>Description</th><th>Permissions</th></tr><tr><td>Administrator</td><td>Role for users that should be administrators.</td><td>*</td></tr><tr><td>Agent Administrator</td><td>Role for users that can configure agents, including authorising and deauthorising agents, deleting agents and accessing the agents administration section.</td><td>Administration (Manage CIAgents) [Edit] [Delete]</td></tr><tr><td>Groups</td><td>Build Contributor</td><td>Role for users that can access and interact with builds, including starting and stopping builds, adding comments and tags to builds and viewing build artifacts.</td><td>Builds (Comment, Pin, Start, Stop, Tag, View Artifacts), Configurations (View), Projects (View) [Edit] [Delete]</td></tr><tr><td>Roles</td><td>Build Promoter</td><td>Role for users that can access and interact with all aspects of builds, including promoting build stages.</td><td>Builds (*), Configurations (View), Projects (View) [Edit] [Delete]</td></tr><tr><td>Access Control</td><td>Build Viewer</td><td>Role for users that can view builds.</td><td>Configurations (View), Projects (View) [Edit] [Delete]</td></tr><tr><td>Continua Server</td><td>CI Server Administrator</td><td>Role for users that can administrate the Continua CI Server settings.</td><td>Administration (Manage CIServer), Projects (*) [Edit] [Delete]</td></tr><tr><td>Event Log</td><td>Configuration Administrator</td><td>Role for users that can administrate configurations, including managing configuration security, creating new configurations, editing and deleting existing configurations. These users also have complete control over all builds.</td><td>Configurations (Administrator), Projects (View) [Edit] [Delete]</td></tr><tr><td>Licences</td><td>Configuration Editor</td><td>Role for users that can edit existing configurations. These users also have complete control over all builds.</td><td>Configurations (Edit), Projects (View) [Edit] [Delete]</td></tr><tr><td>Variables</td><td>Guest</td><td>Role that controls the access of Guest users</td><td>[Edit] [Delete]</td></tr><tr><td>Properties</td><td>Project Administrator</td><td>Role for users that can administrate projects, including managing project security, creating new projects, editing and deleting existing projects. These users also have complete control over all configurations and builds.</td><td>Configurations (Administrator), Projects (*) [Edit] [Delete]</td></tr><tr><td>Notifications</td><td>Project Editors</td><td>Role for project editors.</td><td>Configurations (Edit), Projects (Edit) [Edit] [Delete]</td></tr><tr><td>Publishers</td><td>User</td><td>Default role for all registered users.</td><td>Configurations (View), Projects (View) [Edit] [Delete]</td></tr></table>			Name	Description	Permissions	Administrator	Role for users that should be administrators.	*	Agent Administrator	Role for users that can configure agents, including authorising and deauthorising agents, deleting agents and accessing the agents administration section.	Administration (Manage CIAgents) [Edit] [Delete]	Groups	Build Contributor	Role for users that can access and interact with builds, including starting and stopping builds, adding comments and tags to builds and viewing build artifacts.	Builds (Comment, Pin, Start, Stop, Tag, View Artifacts), Configurations (View), Projects (View) [Edit] [Delete]	Roles	Build Promoter	Role for users that can access and interact with all aspects of builds, including promoting build stages.	Builds (*), Configurations (View), Projects (View) [Edit] [Delete]	Access Control	Build Viewer	Role for users that can view builds.	Configurations (View), Projects (View) [Edit] [Delete]	Continua Server	CI Server Administrator	Role for users that can administrate the Continua CI Server settings.	Administration (Manage CIServer), Projects (*) [Edit] [Delete]	Event Log	Configuration Administrator	Role for users that can administrate configurations, including managing configuration security, creating new configurations, editing and deleting existing configurations. These users also have complete control over all builds.	Configurations (Administrator), Projects (View) [Edit] [Delete]	Licences	Configuration Editor	Role for users that can edit existing configurations. These users also have complete control over all builds.	Configurations (Edit), Projects (View) [Edit] [Delete]	Variables	Guest	Role that controls the access of Guest users	[Edit] [Delete]	Properties	Project Administrator	Role for users that can administrate projects, including managing project security, creating new projects, editing and deleting existing projects. These users also have complete control over all configurations and builds.	Configurations (Administrator), Projects (*) [Edit] [Delete]	Notifications	Project Editors	Role for project editors.	Configurations (Edit), Projects (Edit) [Edit] [Delete]	Publishers	User	Default role for all registered users.	Configurations (View), Projects (View) [Edit] [Delete]	Search... X	
Name				Description	Permissions																																																	
Administrator	Role for users that should be administrators.	*																																																				
Agent Administrator	Role for users that can configure agents, including authorising and deauthorising agents, deleting agents and accessing the agents administration section.	Administration (Manage CIAgents) [Edit] [Delete]																																																				
Groups	Build Contributor	Role for users that can access and interact with builds, including starting and stopping builds, adding comments and tags to builds and viewing build artifacts.	Builds (Comment, Pin, Start, Stop, Tag, View Artifacts), Configurations (View), Projects (View) [Edit] [Delete]																																																			
Roles	Build Promoter	Role for users that can access and interact with all aspects of builds, including promoting build stages.	Builds (*), Configurations (View), Projects (View) [Edit] [Delete]																																																			
Access Control	Build Viewer	Role for users that can view builds.	Configurations (View), Projects (View) [Edit] [Delete]																																																			
Continua Server	CI Server Administrator	Role for users that can administrate the Continua CI Server settings.	Administration (Manage CIServer), Projects (*) [Edit] [Delete]																																																			
Event Log	Configuration Administrator	Role for users that can administrate configurations, including managing configuration security, creating new configurations, editing and deleting existing configurations. These users also have complete control over all builds.	Configurations (Administrator), Projects (View) [Edit] [Delete]																																																			
Licences	Configuration Editor	Role for users that can edit existing configurations. These users also have complete control over all builds.	Configurations (Edit), Projects (View) [Edit] [Delete]																																																			
Variables	Guest	Role that controls the access of Guest users	[Edit] [Delete]																																																			
Properties	Project Administrator	Role for users that can administrate projects, including managing project security, creating new projects, editing and deleting existing projects. These users also have complete control over all configurations and builds.	Configurations (Administrator), Projects (*) [Edit] [Delete]																																																			
Notifications	Project Editors	Role for project editors.	Configurations (Edit), Projects (Edit) [Edit] [Delete]																																																			
Publishers	User	Default role for all registered users.	Configurations (View), Projects (View) [Edit] [Delete]																																																			

Permission Grouping

Permissions in Continua have been grouped so that if you apply a certain permission, any other necessary permissions are automatically included. For example, if you grant someone access to **Edit configuration**, they automatically receive access to **View configurations** as well. Also included with Edit configuration are all the Build Permissions, as a build is an extension of a configuration.

Any of these included permissions can be overridden in the [Access Control](#) section.

Permission Definitions

Name	Includes	Access Granted
Administrator	All permissions	Access to the entire administration section and every other aspect of Continua. Administrators are the only users that can modify global security settings
Manage CI Server	Manage CI agents, all config. and build permissions	Access to the Continuous Integration Administration section. Users need this permission to modify CI properties and set CI Issue Connectors. This also includes agent management and all configuration and build functionality. (Note this permission does not include view project which is required to view configurations)
Manage CI Agents		Access to the Agent administration section. Allows the user to authorise/deauthorise agents and delete agents
Project Administrator	All project permissions	Access to the Project security section. Also allows the user to create, edit and delete projects.
View Project		Can see projects but cannot change any project settings.
Edit Project	View project	Can modify any settings on existing projects. This does not grant access to the project security section.
Create Project	Edit project, view project	Can create new projects and edit existing projects. This does not grant access to the project security section.

Delete Project	Edit project, view project	Can delete existing projects and edit existing projects. This does not grant access to the project security section.
Configuration Administrator	All configuration and build permissions	Grants full permission to configurations and builds. This also includes access to the configuration security section. (Note: to be able to view/modify a configuration, a user must also have View Project permissions on the configuration's parent project)
View Configuration		Can see configurations and builds but cannot edit either the configuration or its builds. This permission does not allow users to start or stop builds (Note: to be able to view/modify a configuration, a user must also have View Project permissions on the configuration's parent project)
Edit Configuration	View Configuration, All build permissions	Can modify any settings on existing configurations. This does not grant access to the configuration security section. This also includes all build permissions. (Note: to be able to view/modify a configuration, a user must also have View Project permissions on the configuration's parent project)
Create Configuration	Edit configuration, view configuration and all build permissions	Can create new configurations and edit existing configurations, including all build actions. This does not grant access to the configuration security section. (Note: to be able to view/modify a configuration, a user must also have View Project permissions on the configuration's parent project)
Delete Configuration	Edit configuration, view configuration and all build permissions	Can delete and edit existing configurations. This does not grant access to the configuration security section. This also includes all build permissions. (Note: to be able to view/modify a configuration, a user must also have View Project permissions on the configuration's parent project)
Start Build		Can start builds. (Note: to be able to view builds, a user must also have view configuration permissions on the build's configuration)
Stop Build		Can stop builds. (Note: to be able to view builds, a user must also have view configuration permissions on the build's configuration)
Promote Stage		Can promote a build to the next stage. (Note: to be able to view builds, a user must also have view configuration permissions on the build's configuration)
View /Download Artifacts		Can view and download artifacts generated by a build. (Note: to be able to view builds, a user must also have view configuration permissions on the build's configuration)
Pin /Unpin Build		Can pin and unpin builds. (Note: to be able to view builds, a user must also have view configuration permissions on the build's configuration)
Add Comment		Can add and edit comments to builds. (Note: to be able to view builds, a user must also have view configuration permissions on the build's configuration)
Tag Builds		Can tag builds. (Note: to be able to view builds, a user must also have view configuration permissions on the build's configuration)

Creating & Editing a Role

Edit Role

Name

Project Editors

Description

Role for project editors.

Permissions

Projects	☐
Project Administrator	☐
View Project	☒
Edit Project	☒
Create Project	☐
Delete Project	☐
Configurations	☐
Configuration Administrator	☐
View Configuration	☒
Edit Configuration	☒
Create Configuration	☐
Delete Configuration	☐
Builds	☒
Start Build	☒
Stop Build	☒
Promote Stage	☒
View/Download Artifacts	☒
Pin/UnPin Build	☒
Add Comment	☒
Tag Builds	☒

✓ Save

✕ Cancel

The permissions list contains every single permission in Continua grouped by category. All permissions that are selected will be applied to the selected role. If a permission is grayed out, then this permission is being included from another permission. For example, if edit configuration is selected then view configuration will also be selected as view is required to edit.

If a checkbox in the category header is selected then it will automatically check every permission in that category.

Once a role has been created it can then be linked to users and groups in the [Access Control](#) section.

Deleting Roles

When a role is deleted, all associated permissions are deleted with it. This means that deleting a role will strip its permissions from any users associated to that role.