

# Stride

The Stride Publisher allows Continua CI to send notifications to Stride users or rooms.

## Stride

**New Notification Publisher**

Publisher

Stride

Options

Required Field

Cloud ID

123e4567-e89b-12d3-a456-426655440000

The cloud id for the site associated with a company, department or team on Stride.

Authentication Method

Client secret

Client Id

A3533b1c269D96e30EDeE96b3E42f43f

The client id for your Stride app. Note that the Stride app must be added to recipient conversations.

Client Secret

e7AcEf013AD8C18Eb007B2704ca9b63fD7010CA6cF1-f95C2512044Bt

The client secret associated with your Stride app.

Validate

Save

Cancel

Help

### Cloud Id

Enter the cloud id for the site associated with your company, department or team. This is a GUID and can be found in the URL for the Stride web app e.g. <https://app.stride.com/123e4567-e89b-12d3-a456-426655440000/lobby>

### Authentication Method

The Stride publisher can authenticate using one of the following methods:

- Access token: generated for a specific Stride conversation.
- Client secret: associated with a Stride app

The access token can be generated by selecting a conversation or room in Stride, choosing Apps on the Stride right-hand sidebar menu and clicking on + to add an App. Click the link to 'Add a custom app', then specify a token name and click Create. Copy the generated access token and paste into the **Access Token** field in the Publisher dialog.

Client secret is the preferred authentication method. A client id and client secret associated with a Stride app can be used by Continua CI to generate a temporary access token which can be used to send messages to all site users and conversations. Create an app at <https://developer.atlassian.com/apps/create>. Ensure that you enable both the Stride API and User API. Then copy the relevant details into the **Client Id** and **Client Secret** fields in the Publisher dialog. Make sure that you copy the Installation URL under the Install tab and install the App into any conversation in your site - select the conversation or room in Stride, choose Apps on the Stride right-hand sidebar menu and click on + to add an App. Click the link to 'Add a custom app', enter the Installation URL and then click Agree.

See [Stride Authentication](#) for further details on Stride authentication.

## Options

New Notification Publisher

Publisher

Stride

Options

Required Field

Subscription Types

☒ Users and groups☒ Conversations

Specify whether subscriptions can be sent only to users and groups, only to room conversations, or to both.

Default Conversation

Specify the default room name (or conversation id) for this publisher. This can be overridden when creating a subscription or in user preferences.

Default Message Format

Panel

Specify the default message format for this publisher. This can be overridden in user preferences

Validate

Save

Cancel

Help

### Enabled Subscription Types

Subscriptions can be set up to send notifications to a specific user, a group of users or a Stride conversation (either directly between users or as a room). Tick the subscription types that are allowed for this publisher.

### Default Conversation

Specify the default conversation id or room name to use when setting up a subscription for this publisher.

### Default Message Format

Specify the default message format to use when setting up a subscription for this publisher. The options are: Text, Markdown, Card or Panel. [Templates](#) are provided for describing the content for each of these formats. The Card and Panel format template are written using the [Atlassian Document Format](#). See [Sending Stride messages as Markdown](#) for details of Markdown format.