

# Upload Azure File Action

 This action is a wrapper for the Azure command lines: [az storage file upload](#) | [az storage file upload-batch](#). If you're having trouble using this action, or any of the Azure actions, please refer to the [Azure command line reference](#).

The Upload Azure File action is a [premium action](#) that can be used to upload files to a [file share](#) under the specified account on Azure.

Before uploading files, you will need a [Storage Account](#) and a [File Share](#). See also the [Delete Azure File Action](#).

## Upload Azure File

**Upload Azure File Action** Premium

**Upload Azure File** | Authentication | Storage Account | Settings | Headers | Options | Environment | Comments

**Name**  Required Field

Enabled

**Working Folder**    
Optional working folder for running the executable. Defaults to the workspace folder.

**Authentication Actions**  Login  Logout  
Choose whether to log in to Azure before running the command and logout after running the command.

Batch upload all files in folder matching pattern

**Source File**    
Path to the source file to upload. [--source]

**File Share Name**    
The destination file share which the file(s) will be uploaded to. [--container-name | --destination]

**Path**    
The destination path within the file share to upload the files to. If the file name is omitted, the source file name will be used. [--path]

**Using**

### Name

A friendly name for this action (will be displayed in the [actions workflow area](#)).

### Enabled

Determines if this action will be run within the relevant stage.

### Working Folder

The folder where the command line executable is run. This is optional and defaults to the workspace folder.

### Authentication Actions

Generally you will need to log in to Azure before running this action and log out afterwards. If you have several Azure actions in a stage, you can avoid repeated logins by unchecking the Login action on all but the first Azure action and unchecking the Logout action on all but the last Azure action. The Authentication tab will be shown if either of these options is ticked.

### Batch upload all files in folder matching pattern

Specifies whether one or multiple files are to be uploaded from the folder.

## Source File

The path to the source file to upload. [--source]

## File Share Name

The destination file share which the file(s) will be uploaded to. [--container-name | --destination]

## Path

The destination path within the file share to upload the files to. If the file name is omitted, the source file name will be used. [--path]

If the **'Batch delete all files in file share matching pattern'** checkbox is ticked

Upload Azure File Action Premium

Upload Azure File | Authentication | Storage Account | Settings | Headers | Options | Environment | Comments

**Name**  Required Field

Enabled

**Working Folder**  📁  
Optional working folder for running the executable. Defaults to the workspace folder.

**Authentication Actions**  Login  Logout  
Choose whether to log in to Azure before running the command and logout after running the command.

Batch upload all files in folder matching pattern

**Source Folder**  📁  
Path to the source folder to batch upload to Azure. [--source]

**Pattern**  🔍 📁  
A globbing pattern used to select files in the source folder and its subfolders. Leave blank to match all files. [--pattern]

**File Share Name**  📁  
The destination file share which the file(s) will be uploaded to. [--container-name | --destination]

**Destination Path**  📁  
The destination folder within the file share to upload the files to. [--destination-path]

**Using**  ▼

Validate

## Source Folder

The path to the source folder to upload to Azure as a batch. [--source]

## Pattern

A globbing pattern used to select files in the source folder and its subfolders. [--pattern]

The supported pattern characters are:

- \* Matches zero or more of any character.
- ? Matches exactly one of any character.
- [seq] Matches one character of any of the characters within the square brackets.
- [!seq] Matches one character which is not one of the characters within the square brackets.

Note that matching is case-insensitive.

## File Share Name

The destination file share which the file(s) will be uploaded to. [--container-name | --destination]

## Destination Path

The destination directory within the file share to upload the files to. [--destination-path]

## Using

The version of the Azure command line to use. It is important that the agent has the correct version of the Azure command line installed for command provided.

The Using drop down is populated with any property collector whose namespace matches the pattern defined by the Create Azure Resource Group action. The pattern for this action is `^Azure.Cli.*`

If you create a property collector for this action, make sure you select the **Path Finder Plugin** type and give it a name that will match the pattern above in blue. Example names listed [here](#), search the table's Plugin column for "**Azure Command**".

For more in-depth explanations on property collectors see [Property Collectors](#).

Alternatively, you can select the **Custom** option from the Using drop down list and specify a path in the resulting input field that will be displayed. Please read [Why it's a good idea to use a property collector](#) before using this option.

## Authentication

**Upload Azure File Action** Premium

Upload Azure File **Authentication** Storage Account Settings Headers Options Environment Comments

Sign in/out using service principal [login --service-principal]

Username  [login | logout --username] ✓

Password  User's password [login --password] ✓

Validate Save Cancel Help

### Sign in/out using service principal

Tick this to log in or out using a service principal instead of a username and password. An Azure service principal is an identity created for use with applications, hosted services, and automated tools to access Azure resources. This access is restricted by the roles assigned to the service principal, giving you control over which resources can be accessed and at which level. For security reasons, it's always recommended to use service principals with automated tools rather than allowing them to log in with a user identity. [login --service-principal]

### [Username / Password Authentication](#)

#### Username

Enter a username to log into the Azure cloud. This is generally an email address. [login|logout --username]

### Password

The password associated with the Azure username. [login --username]

### Service Principal Authentication

The screenshot shows the 'Upload Azure File Action' dialog box with the 'Authentication' tab selected. The dialog has a blue header with the title 'Upload Azure File Action' and a 'Premium' label in the top right. Below the header is a navigation bar with tabs: 'Upload Azure File', 'Authentication', 'Storage Account', 'Settings', 'Headers', 'Options', 'Environment', and 'Comments'. The 'Authentication' tab is active. The main area contains several fields and options:

- A checkbox labeled 'Sign in/out using service principal [login --service-principal]' is checked.
- A 'Name or URL' field with a required field indicator (orange bar) and a green checkmark icon. Below it is the text: 'The URL or name associated with the service principal. [login |logout --username]'
- A 'Client Secret or Certificate' field with a green checkmark icon and a blue eye icon. Below it is the text: 'Client secret or a pem file with key and public X509 certificate used to create the service principal. [login --password]'
- A 'Tenant' field with a green checkmark icon. Below it is the text: 'The tenant associated with the service principal, as either an .onmicrosoft.com domain or Azure object ID. [login --tenant]'
- A checkbox labeled 'Use certificate SN issuer [login --use-cert-sn-issuer]' is unchecked.

At the bottom of the dialog are three buttons: 'Validate' (with a checkmark icon), 'Save' (with a floppy disk icon), 'Cancel' (with an 'X' icon), and 'Help' (with a question mark icon).

### Name or URL

Enter the application name or the URL associated with the service principal. [login --service-principal --username]

### Client Secret or Certificate

Enter the service principal password, or the path to a X509 certificate used to create the service principal in PEM format. [login --service-principal --password]

### Tenant

Enter the tenant associated with the service principal, as either an [.onmicrosoft.com](https://onmicrosoft.com) domain or Azure object ID. [login --service-principal --tenant]

### Use certificate SN issuer

Tick to support automatic certificate rollovers with service principals configured with Subject Name and Issuer Authentication. [login --use-cert-sn-issuer]

### Storage Account

Upload Azure File Action Premium

Upload Azure File Authentication **Storage Account** Settings Headers Options Environment Comments

Required Field

Use connection string

Account Name   

The name of your storage account. [--account-name]

Use Shared Access Signature (SAS) token

Account Key  

The primary or secondary access key for your storage account. [--account-key]

### Use connection string

If this is ticked, a connection string is used.

### Connection String

This field is visible only if the **Use Connection String** checkbox is ticked.

The connection string for your storage account. [--connection-string]

### Account Name

The name of your storage account. [--account-name]

### Use Shared Access Signature (SAS) token

If this is ticked, a shared access signature (SAS) token is used.

### SAS Token

This field is visible only if the **Use Shared Access Signature (SAS) token** checkbox is ticked.

Enter a shared access signature token. A [shared access signature \(SAS\)](#) provides you with a way to grant limited access to objects in your storage account to other clients, without exposing your account key. This is used in conjunction with storage account name. [--sas-token]

### Account Key

The primary or secondary [access key](#) for your storage account. [--account-key]

You can get these keys into variables using the [Get Azure Storage Account Keys Action](#).

## Settings

**Upload Azure File Action** Premium

Upload Azure File   Authentication   Storage Account   **Settings**   Headers   Options   Environment   Comments

Required Field

**Maximum Connections**

Maximum number of parallel connections. Default is 1. [--max-connections]

**Validate content**  
Specifies that an MD5 hash shall be calculated for each chunk of the file and verified by the service when the chunk has arrived. [--validate-content]

**Subscription**

Name or ID of the subscription. Leave blank for default. [--subscription]

### Maximum Connections

The maximum number of parallel connections. The default is 1. [--max-connections]

### Validate content

Specifies that an MD5 hash shall be calculated for each chunk of the file and verified by the service when the chunk has arrived. [--validate-content]

### Command Timeout (in seconds)

The time in seconds to wait for the directory to be created. Leave zero to wait until complete. [--timeout]

### Subscription

The name or ID of the subscription to use. If omitted the default subscription for your environment will be used. [--subscription]

## Headers

Upload Azure File Action
Premium

---

Upload Azure File
Authentication
Storage Account
Settings
Headers
Options
Environment
Comments

| Required Field

<b>Content Cache Control</b>	max-age=300, must-revalidate	
	A string defining the content caching policy. [--content-cache-control]	
<b>Content Disposition</b>	attachment; filename=	
	A header indicating how the content is expected to be displayed. [--content-disposition]	
<b>Content Encoding</b>	gzip, identity	
	Defines the encoding used to compress the content. [--content-encoding]	
<b>Content Language</b>	en-AU, en-US	
	Describes the intended language(s) of the content. [--content-language]	
<b>Content MD5 Hash</b>		
	An MD5 hash which can be used to verify the content. [--content-md5]	
<b>Content MIME Type</b>	text/html; charset=utf-8	
	The content MIME type header describing the type of content. [--content-type]	

Validate

Save

Cancel

Help

### Content Cache Control

A string defining the content caching policy. [--content-cache-control]

### Content Disposition

A header indicating how the content is expected to be displayed. [--content-disposition]

### Content Encoding

Defines the encoding used to compress the content. [--content-encoding]

### Content Language

Describes the intended language(s) of the content. [--content-language]

### Content MD5 Hash

An MD5 hash which can be used to verify the content. [--content-md5]

### Content MIME Type

The content MIME type header describing the type of content. [--content-type]

## Options

**Upload Azure File Action** Premium

Upload Azure File Authentication Storage Account Settings Headers **Options** Environment Comments

Required Field

**Log Level**

**Timeout (in seconds)**   
How long to wait for the action to finish running before timing out. Leaving this blank (or zero) will default to 86400 seconds (24 hours).

**No Response Timeout (in seconds)**   
How many seconds to wait for the Azure commands to respond with output before timing out. Leave zero to wait until the main timeout.

**Treat failure as warning**  
Tick to continue build on failure marking the action with a warning status.

**Ignore warnings**

### Log Level

The amount of information detail to display in the build log.

### Timeout (in seconds)

How long to wait for the action to finish running before timing out. Leaving this blank (or zero) will default to 86400 seconds (24 hours).

### No Response Timeout (in seconds)

How many seconds to wait for the Azure commands to respond with output before timing out. Leave zero to wait until the main timeout.

### Treat failure as warning

Tick to continue build on failure marking the action with a warning status.

### Ignore warnings

If this is ticked, any warnings logged will not mark the action with a warning status.

## Environment

**Upload Azure File Action** Premium

Upload Azure File   Authentication   Storage Account   Settings   Headers   Options   **Environment**   Comments

Environment Variables Required Field

variable\_name=variable\_value

Specify one name & value pair per line.

Log environment variables

Generate system environment variables  
Tick this to set new environment variables prefixed with 'ContinuaCI.' for system objects and variables.

### Environment Variables

Multiple environment variables can be defined - one per line. These are set before the command line is run.

### Log environment variables

If this is ticked, environment variable values are written to the build log.

### Generate system environment variables

Tick this checkbox to set up a list of new environment variables prefixed with 'ContinuaCI.' for all current system expression objects and variables.

### Mask sensitive variable values in system environment variables

This checkbox is visible only if the 'Generate system environment variables' checkbox is ticked.

If this is ticked, the values of any variables marked as sensitive will be masked with \*\*\*\* when setting system environment variables. Clear this to expose the values.