

Application Variables

Application Variables are defined by FinalBuilder at start-up. The actual variables available will depend on which software you have installed on your machine. Application Variables cannot be modified.

These Application Variables are available on all machines :

SYSDIR	The Windows System Directory, eg. 'D:\WINNT\System32'
WINDIR	The Windows Directory - eg. 'D:\WINNT'
COMPUTERNAME	The name of the computer you are running FinalBuilder on.
USERNAME	The Name of the currently logged on User
DOSCMD	The path to the DOS command interpreter. This is used internally by FinalBuilder.

The following Application Variables are created by FinalBuilder:

ISAUTOBUILD	True if the build is being run automatically from a command line parameter .
ISCONSOLEBUILD	True if the build is being run from the console under FBCMD.EXE.
ISINTERACTIVEBUILD	True if the build is being run under the FinalBuilder IDE.
ISINCLUDEDPROJECT	True if the current project is being run as a child project (via the Include FinalBuilder Project Action)
FBPROJECT	The full path to the currently running FinalBuilder project file.
FBPROJECTDIR	The dir where the currently running FinalBuilder project lives.
FBDIR	The directory in which FinalBuilder is installed.
FBIGNOREDERRORS	The number of actions in error during the build that were ignored.
FBBUILDTYPE	When running in the IDE, is this a full run or a run started part-way through? Possible values are script constants btFull, btFromCurrent, btSelected or btSelectedAndChildren.
ISSERVERBUILD	True if the project is being run by FinalBuilder Server.
FBSERVERPROJECTNAME	If the project is run by FinalBuilder Server, holds the name of the project as it is defined there

These Variables may appear on your system, depending on whether you have the software installed :

VB6	The path to the Visual Basic 6 compiler
DELPHI3DIR	The directory where Delphi 3 is installed
DELPHI3	The path to the Delphi 3 command line compiler
DELPHI3_BRCC32	The path to the Delphi 3 Resource compiler
DELPHI4DIR	The directory where Delphi 4 is installed
DELPHI4	The path to the Delphi 4 command line compiler
DELPHI4_BRCC32	The path to the Delphi 4 Resource compiler
DELPHI5DIR	The directory where Delphi 5 is installed

DELPHI5	The path to the Delphi 5 command line compiler
DELPHI5_BRCC32	The path to the Delphi 5 Resource compiler
DELPHI6DIR	The directory where Delphi 6 is installed
DELPHI6	The path to the Delphi 6 command line compiler
DELPHI6_BRCC32	The path to the Delphi 6 Resource compiler
DELPHI7DIR	The directory where Delphi 7 is installed
DELPHI7	The path to the Delphi 7 command line compiler
DELPHI7_BRCC32	The path to the Delphi 7 Resource compiler
DELPHI8DIR	The directory where Delphi.NET 8 is installed
DELPHI8	The path to the Delphi 8 command line compiler (dccil.exe)
DELPHI2005	The path to the Delphi 2005 command line compiler
DELPHI2005DIR	The directory where Delphi 2005 is installed
DELPHI2005_BRCC32	The path to the Delphi 2005 Resource compiler
DELPHI2005DOTNET	The path to the Delphi 2005 .Net command line compiler (dccil.exe)
DELPHI2006DIR	The directory where Delphi 2006 is installed
DELPHI2006_BRCC32	The path to the Delphi 2006 Resource compiler
DELPHI2006DOTNET	The path to the Delphi 2006 .Net command line compiler (dccil.exe)
DELPHI2007DIR	The directory where Delphi 2007 is installed
DELPHI2007_BRCC32	The path to the Delphi 2007 Resource compiler
DELPHI2007DOTNET	The path to the Delphi 2007 .Net command line compiler (dccil.exe)
BDSUSERDIR	The Embarcadero Studio Projects user directory
AQTestErrors	The AQ Test Complete error count
AQTestWarnings	The AQ Test Complete warning count
CB2007DIR	The directory where CBuilder 2007 is installed
CB2007	The path to CBuilder 2007 make.exe
CB2007DCC	The path to the CBuilder 2007 Delphi command line compiler (dcc32.exe)
CB2007_BRCC32	The path to the CBuilder 2007 command line compiler (brcc32.exe)
BCB2006DIR	The directory where CBuilder 2006 is installed
BCB2006	The path to CBuilder 2006 make.exe
BCB2006DCC	The path to the CBuilder 2006 Delphi command line compiler (dcc32.exe)
BCB2006_BRCC32	The path to the CBuilder 2006 command line compiler (brcc32.exe)
BCB3DIR	The directory where CBuilder 3 is installed
BCB3	The path to CBuilder 3 make.exe
BCB3DCC	The path to the CBuilder 3 Delphi command line compiler (dcc32.exe)
BCB3_BRCC32	The path to the CBuilder 3 command line compiler (brcc32.exe)
BCB4DIR	The directory where CBuilder 4 is installed

BCB4	The path to CBuilder 4 make.exe
BCB4DCC	The path to the CBuilder 4 Delphi command line compiler (dcc32.exe)
BCB4_BRCC32	The path to the CBuilder 4 command line compiler (brcc32.exe)
BCB5DIR	The directory where CBuilder 5 is installed
BCB5	The path to CBuilder 5 make.exe
BCB5DCC	The path to the CBuilder 5 Delphi command line compiler (dcc32.exe)
BCB5_BRCC32	The path to the CBuilder 5 command line compiler (brcc32.exe)
BCB6DIR	The directory where CBuilder 6 is installed
BCB6	The path to CBuilder 6 make.exe
BCB6DCC	The path to the CBuilder 6 Delphi command line compiler (dcc32.exe)
BCB6_BRCC32	The path to the CBuilder 6 command line compiler (brcc32.exe)
DOCOMATICDIR	The directory where Doc-O-Matic is installed
DOCOMATIC	The path to the Doc-O-Matic command line compiler