

String Quoting Action

The String Quoting action allows you to add or remove quotes from a string.

Input And Output

The screenshot shows the 'String Quoting' dialog box with the 'Input and Output' tab selected. The dialog has a title bar with a close button (X) and a tab bar with four tabs: 'General', 'Runtime', 'Input and Output' (active), and 'Quoting Options'. The 'Input' section has a label with a '%' icon and a text field. Below it are two radio buttons: 'From variable' (selected) and 'Specify value'. The 'From variable' option has a dropdown menu showing 'L_File'. The 'Specify value' option has an empty text field. The 'Output' section also has a label with a '%' icon and a text field. Below it are two radio buttons: 'Apply to existing value' (selected) and 'Specify output variable'. The 'Specify output variable' option has an empty text field. At the bottom are three buttons: 'OK', 'Cancel', and 'Help'.

Input

From variable

Use string from existing variable.

Specify value

Input a new string to use.

Output


Apply to existing variable

Output changes to original variable.

Specify output variable

Output changes to specific variable.

Quoting Options



Quoting options

Add Single Quotes

Single quotes will be added to the beginning and end of a string.

Add Double Quotes

Double quotes will be added to the beginning and end of a string.

Strip Quotes

This action will remove one pair of matching quotes from a string.

Force Quoting

By default this action checks for quotes before adding them, enabling this option prevents this, which enables you to add extra quotes to a string.

Scripting Info

The Action properties available are :

property InputString : string;// The input string, if not using a variable

property OutputVariable: string;// The Output Variable name

property ApplyToInput : boolean;// Apply the changes to the input variable, only valid if using an input variable

property UsingInputVariable : boolean;// True if using an input variable, not input string

property InputVariable : string;// Input variable name

property AddDoubleQuotes : boolean;//True to Add Double Quotes, otherwise false

property AddSingleQuotes : boolean;//True to Add Single Quotes, otherwise false

property StripQuotes : boolean;//True to Strip Quotes, otherwise false

property ForceQuoting : boolean;//True to Force Quoting